

Oracle® GoldenGate
Oracle TimesTen Installation and Setup
Guide
11g Release 1 (11.1.1)
E17808-01

October 2010

ORACLE®

Copyright © 1995, 2010 Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

.....

Chapter 1	System requirements and preinstallation instructions	3
	Overview of Oracle GoldenGate for TimesTen	3
	Supported platforms.....	3
	Operating system requirements.....	3
	Database requirements.....	6
	Non-supported items.....	6
	Supported and non-supported object names	6
	Object names and owners	6
	Case sensitivity.....	6
	Supported characters.....	7
	Non-supported characters.....	8
Chapter 2	Installing Oracle GoldenGate	9
	Installation overview.....	9
	Upgrades	9
	New installations	9
	Downloading Oracle GoldenGate	9
	Setting library paths for dynamic builds on UNIX systems	10
	Installing Oracle GoldenGate on Linux and UNIX.....	11
	Installing the Oracle GoldenGate files	11
	Configuring Manager and other processes	12
	Installing Oracle GoldenGate on Windows and Windows Cluster.....	12
	Installing Oracle GoldenGate into a Windows Cluster	12
	Installing the Oracle GoldenGate files	12
	Specifying a custom Manager name	12
	Installing Manager as a Windows service	13
	Adding Oracle GoldenGate as a Windows cluster resource.....	14
	Configuring Manager and other processes	16
Chapter 3	Uninstalling Oracle GoldenGate	17
	Uninstalling Oracle GoldenGate from UNIX.....	17
	Uninstalling Oracle GoldenGate from Windows (non-cluster)	17

.....

Uninstalling Oracle GoldenGate from Windows Cluster.....	18
Appendix 1 Oracle GoldenGate installed components	19
Oracle GoldenGate Programs and Utilities.....	19
Oracle GoldenGate subdirectories	21
Other Oracle GoldenGate files	23
Oracle GoldenGate checkpoint table	26
Index	27

CHAPTER 1

System requirements and preinstallation instructions

.....

Overview of Oracle GoldenGate for TimesTen

Oracle GoldenGate for TimesTen supports the delivery of data from other types of databases to a TimesTen database.

High-speed Oracle GoldenGate replication can be used to refresh a TimesTen cache environment with minimal latency. In addition, with its heterogeneous support, Oracle GoldenGate enables the TimesTen data store to be used as a data integration point for other data sources.

Oracle GoldenGate supports the mapping, filtering, and manipulation of data from other sources to the TimesTen database. Oracle GoldenGate does not support the extraction of data from TimesTen to other TimesTen data stores or to other kinds of databases.

Supported platforms

To find out which Oracle GoldenGate builds are available for a specific combination of database version and operating system, log onto <http://support.oracle.com> and select the **Certifications** tab. For assistance, click **Tips for Finding Certifications**.

An email and password are required to enter this site.

Operating system requirements

Memory requirements

The amount of memory that is required for Oracle GoldenGate depends on the number of concurrent processes that will be running.

- The Oracle GoldenGate GGSCI command interface fully supports up to 300 concurrent Replicat processes per instance of Oracle GoldenGate. An instance of Oracle GoldenGate equates to one Manager process, which is the main controller process.
- Each Replicat process needs approximately 25-55 MB of memory, or more depending on the size of the transactions and the number of concurrent transactions.

.....

Disk requirements

Assign the following free disk space:

- 50-150 MB, depending on the database and platform. This includes space for the compressed download file and space for the uncompressed files. You can delete the download file after the installation is complete.
- 40 MB for the working directories and binaries for each instance of Oracle GoldenGate that you are installing on the system. For example, to install two builds of Oracle GoldenGate into two separate directories, allocate 80 MB of space.
- To install Oracle GoldenGate into a cluster environment, install the Oracle GoldenGate binaries and files on a shared file system that is available to all cluster nodes.
- Additional disk space on any system that hosts Oracle GoldenGate trails, which are files that contain the working data. The space that is consumed by the trails varies, depending on the volume of data that will be processed. A good starting point is 1 GB. See the following guidelines.

Storage for Oracle GoldenGate trails

To prevent trail activity from interfering with business applications, assign a separate disk or file system to contain the trail files. These files are created during processing to store all of the data that is captured by Oracle GoldenGate. The default size is 10 megabytes, but can be changed during the configuration process. Trail files accumulate but can be purged according to rules set with the PURGEOLDEXTRACTS parameter.

Trail files can reside on drives that are local to the Oracle GoldenGate installation, or they can reside on NAS or SAN devices. You will specify the location of the trails when you configure Oracle GoldenGate.

For trails at the target location, provide enough disk space to handle data accumulation according to the purge rules set with PURGEOLDEXTRACTS. Even with PURGEOLDEXTRACTS in use, data will always accumulate on the target because it is transferred across the network faster than it can be applied to the target database.

To estimate required trail space

1. Estimate the longest time that the network could be unavailable. Plan to store enough data to withstand the longest possible outage, because otherwise you will need to resynchronize the source and target data if the outage outlasts disk capacity.
2. Estimate how much transaction log volume your business applications generate in one hour.
3. Use the following formula to calculate the required disk space.

[log volume in one hour] x [number of hours downtime] x .4 = trail disk space

This equation uses a multiplier of 40 percent because only about 40 percent of the data in a transaction log is needed by Oracle GoldenGate.

NOTE This formula is a conservative estimate, and you should run tests once you have configured Oracle GoldenGate to determine exactly how much space you need.

TCP/IP

- Configure the system to use TCP/IP services, including DNS.
- Configure the network with the host names or IP addresses of all systems that will be hosting Oracle GoldenGate processes and to which Oracle GoldenGate will be connecting. Host names are easier to use.
- Oracle GoldenGate requires the following unreserved and unrestricted TCP/IP ports:
 - One port for communication between the Manager process and other Oracle GoldenGate processes.
 - A range of ports for local Oracle GoldenGate communications: can be the default range starting at port 7840 or a customized range of up to 256 other ports.
- Keep a record of the ports you assigned to Oracle GoldenGate. You will specify them with parameters when configuring the Manager process.
- Configure your firewalls to accept connections through the Oracle GoldenGate ports.

Operating system privileges

- To install on UNIX, the user installing Oracle GoldenGate must have read and write privileges on the Oracle GoldenGate installation directory.
- The Oracle GoldenGate processes require an operating system user that has privileges to read, write, and delete files and subdirectories in the Oracle GoldenGate directory. In addition, the user for the Manager process requires privileges to control Oracle GoldenGate processes.
- Dedicate these operating system users to Oracle GoldenGate. Sensitive information might be available to anyone who runs an Oracle GoldenGate process.

Itanium requirements

To install Oracle GoldenGate on a Microsoft Itanium system, the vcredist_IA64.exe runtime library package must be installed. You can download this package from the Microsoft website. This package includes VisualStudio DLLs necessary for Oracle GoldenGate to operate on the Itanium platform. If these libraries are not installed, Oracle GoldenGate generates the following error.

"The application failed to initialize properly (0xc0150002). Click on Ok to terminate the application.

Third-party programs

- Before installing Oracle GoldenGate on a Windows system, install and configure the Microsoft Visual C++ 2005 SP1 Redistributable Package. **Make certain it is the SP1 version of this package, and make certain to get the correct bit version for your server.** This package installs runtime components of Visual C++ Libraries. For more information, and to download this package, go to <http://www.microsoft.com>.
- Oracle GoldenGate fully supports virtual machine environments created with any virtualization software on any platform. When installing Oracle GoldenGate into a virtual machine environment, select a build that matches the database and the operating system of the virtual machine, not the host system.

Database requirements

Database user

- Create a database user that is dedicated to Oracle GoldenGate. It can be the same user for all of the Oracle GoldenGate processes that must connect to a database:
 - Replicat (target database)
 - DEFGEN (source or target database)
- To preserve the security of your data, and to monitor Oracle GoldenGate processing accurately, do not permit other users, applications, or processes to log on as, or operate as, the Oracle GoldenGate database user.
- Keep a record of the database users. They are required in the USERID parameter.
-

Non-supported items

- Extraction of DML operations
- Extraction or replication of DDL (data definition language) operations

Supported and non-supported object names

Object names and owners

Source and target object names must be fully qualified in Oracle GoldenGate parameter files, as in fin.emp. Oracle GoldenGate supports character case as follows.

Case sensitivity

The following are general guidelines for the case-sensitivity of object names as it relates to Oracle GoldenGate. These guidelines may or may not apply to your databases, depending on whether the database or the underlying operating system supports case-sensitivity. Keep in mind that case-sensitivity (or lack thereof) may apply to the source database but not the target, or to the target but not the source.

- If the system or database is case-sensitive, Oracle GoldenGate supports the case sensitivity of database names, owner and schema names, object names, column names, and user names.
- If the system or database is case-insensitive (or is configured for case-insensitivity), Oracle GoldenGate converts all names to upper case.

To preserve case-sensitivity in an Oracle GoldenGate configuration

In Oracle GoldenGate parameter files, specify case-sensitive names exactly as they appear in the database. In TABLE and MAP parameters, enclose case-sensitive names in double quotes if the other database (the source or target of the case-sensitive objects) is not case-sensitive.

If replicating from a case-insensitive source to a case-sensitive target, enter the source names in upper case in the Replicat MAP statements, to reflect the fact that Extract writes them to the trail as uppercase.

For example:

```
MAP SALES.CUSTOMER, TARGET "Sales.Account";
```

Supported characters

Oracle GoldenGate supports alphanumeric characters in object names and in the names of key columns and non-key columns. Oracle GoldenGate also supports the following non-alphanumeric characters in columns that are not being used by Oracle GoldenGate as a key.

Table 1 Supported non-alphanumeric characters in object names and non-key column names¹

Character	Description
~	Tilde
<>	Greater-than and less-than symbols
/	Forward slash
\	Backward slash
!	Exclamation point
@	At symbol
#	Pound symbol
\$	Dollar symbol
%	Percent symbol
^	Caret symbol
()	Open and close parentheses
_	Underscore
-	Dash
+	Plus sign
=	Equal symbol
	Pipe
[]	Begin and end brackets
{}	Begin and end curly brackets (braces)

¹ The type of key that is being used by Oracle GoldenGate depends on the definition of a given table and whether there are any overrides by means of a KEYCOLS clause. Oracle GoldenGate will use a primary key, if available, or a unique key/index (selection is dependent on the database). In the absence of those definitions, all columns of the table are used, but a KEYCOLS clause overrides all existing key types. For columns that are being used by Oracle GoldenGate as a key, the characters in the names must be valid for inclusion in a WHERE clause. This list is all-inclusive; a given database platform may or may not support all listed characters.

Non-supported characters

Oracle GoldenGate does not support the following characters in object or column names.

Table 2 Non-supported characters in object and column names¹

Character	Description
&	Ampersand
*	Asterisk
?	Question mark
:	Colon
;	Semi-colon
,	Comma
'	Single quotes
“ ”	Double quotes
‘	Accent mark (Diacritical mark)
.	Period
	Space

¹ This list is all-inclusive; a given database platform may or may not support all listed characters.

CHAPTER 2

Installing Oracle GoldenGate



Installation overview

These instructions are for installing Oracle GoldenGate for the first time. Installing Oracle GoldenGate installs all of the components required to run and manage the processing (exclusive of any components required from other vendors, such as drivers or libraries) and it installs the Oracle GoldenGate utilities. The installation process takes a short amount of time.

Upgrades

To upgrade Oracle GoldenGate from one version to another, follow the instructions on <http://www.oracle.com/technology/software/products/goldengate/index.html>.

New installations

To install Oracle GoldenGate for the first time, the following steps are required:

- Downloading Oracle GoldenGate
- Setting library paths for dynamic builds
- Installing the Oracle GoldenGate software

NOTE Before proceeding, make certain that you have reviewed the System Requirements.

Downloading Oracle GoldenGate

1. Navigate to <http://edelivery.oracle.com>.
2. On the **Welcome** page:
 - Select your language.
 - Click **Continue**.
3. On the **Export Validation** page:
 - Enter your identification information.
 - Accept the **Trial License Agreement** (even if you have a permanent license).
 - Accept the **Export Restrictions**.
 - Click **Continue**.



4. On the **Media Pack Search** page:
 - Select the **Oracle Fusion Middleware** Product Pack.
 - Select the platform on which you will be installing the software.
 - Click **Go**.
5. In the **Results List**:
 - Select the Oracle GoldenGate Media Pack that you want.
 - Click **Continue**.
6. On the **Download** page:
 - Click **Download** for each component that you want. Follow the automatic download process to transfer the mediapack.zip file to your system.

NOTE Before installing the software, review the release notes for any new features, new requirements, or bug fixes that affect your current configuration.

Setting library paths for dynamic builds on UNIX systems

Oracle GoldenGate uses shared libraries. When you install Oracle GoldenGate on a UNIX system, the following must be true *before you run GGSCI or any other Oracle GoldenGate process*.

1. Make certain that the database libraries are added to the shared-library environment variables of the system. This procedure is usually performed at database installation time. Consult your Database Administrator if you have any questions.
2. If you will be running an Oracle GoldenGate program from outside the Oracle GoldenGate installation directory on a UNIX system:
 - (Optional) Add the Oracle GoldenGate installation directory to the PATH environment variable.
 - (Required) Add the Oracle GoldenGate installation directory to the shared-libraries environment variable.

For example, given an Oracle GoldenGate installation directory of /ggs/10.0, the second command in the following table requires these variables to be set:

Command	Requires GG libraries in environment variable?
\$ ggs/10.0 > ./ggsci	No
\$ ggs > ./10.0/ggsci	Yes

To set the variables in Korn shell

```
PATH=<installation directory>:$PATH
export PATH
<shared libraries variable>=<absolute path of installation directory>:$<shared libraries variable>
export <shared libraries variable>
```

To set the variables in Bourne shell

```
export PATH=<installation directory>:$PATH  
export <shared libraries variable>=<absolute path of installation directory>:$<shared libraries variable>
```

To set the variables in C shell

```
setenv PATH <installation directory>:$PATH  
setenv <shared libraries variable> <absolute path of installation directory>:$<shared libraries variable>
```

Where: <shared libraries variable> is one of the following:

UNIX/Linux library path variables per platform

Platform ¹	Environment variable
◆ IBM AIX	LIBPATH
◆ IBM z/OS	
HP-UX	SHLIB_PATH
◆ Sun Solaris	LD_LIBRARY_PATH
◆ HP Tru64 (OSF/1)	
◆ LINUX	

¹ A specific platform may or may not be supported by Oracle GoldenGate for your database. See the Systems Requirements for supported platforms.

Example `export LD_LIBRARY_PATH=/ggs/10.0:$LD_LIBRARY_PATH`

NOTE To view the libraries that are required by an Oracle GoldenGate process, use the `ldd <process>` shell command before starting the process. This command also shows an error message for any that are missing.

Installing Oracle GoldenGate on Linux and UNIX

Installing the Oracle GoldenGate files

1. Extract the Oracle GoldenGate mediapack.zip file to the system and directory where you want Oracle GoldenGate to be installed.
2. Run the command shell and change directories to the new Oracle GoldenGate directory.
3. From the Oracle GoldenGate directory, run the GGSCI program.

```
GGSCI
```

4. In GGSCI, issue the following command to create the Oracle GoldenGate working directories.

```
CREATE SUBDIRS
```

5. Issue the following command to exit GGSCI.

```
EXIT
```

Configuring Manager and other processes

- To use Oracle GoldenGate, you must configure the Manager process. You must specify a TCP/IP port for Manager to use, and you can specify optional parameters that control dynamic port assignments, trail file maintenance, and other properties.
- To configure other required processes, Oracle GoldenGate security, and other features that enable you to customize Oracle GoldenGate, see the *Oracle GoldenGate Windows and UNIX Administrator's Guide*.

Installing Oracle GoldenGate on Windows and Windows Cluster

Installing Oracle GoldenGate into a Windows Cluster

1. Log into one of the nodes in the cluster.
2. For the Oracle GoldenGate installation location, choose a drive that is a resource within the same cluster group that contains the database instance.
3. Ensure that this group is owned by the cluster node that you are logging into.
4. Install Oracle GoldenGate according to the following instructions.

Installing the Oracle GoldenGate files

1. Unzip the downloaded file(s) by using WinZip or an equivalent compression product.
2. Move the files in binary mode to a folder on the drive where you want to install Oracle GoldenGate. *Do not* install Oracle GoldenGate into a folder that contains spaces in its name, even if the path is in quotes, for example C:\“Oracle GoldenGate”.
3. From the Oracle GoldenGate folder, run the GGSCI program.
4. In GGSCI, issue the following command to create the Oracle GoldenGate working directories.

```
CREATE SUBDIRS
```

5. Issue the following command to exit GGSCI.

```
EXIT
```

Specifying a custom Manager name

You must specify a custom name for the Manager process if either of the following is true:

- you want to use a name for Manager other than the default of GGSMGR.
- there will be multiple Manager processes running as Windows services on this system, such as one for the Oracle GoldenGate replication software and one for Oracle GoldenGate Veridata. Each Manager on a system must have a unique name. Before proceeding further, verify the names of any local Manager services.

To specify a custom Manager name

1. From the directory that contains the Manager program, run GGSCI.
2. Issue the following command.

```
EDIT PARAMS ./GLOBALS
```
3. In the file, add the following line, where <name> is a one-word name for the Manager service.

```
MGRSERVNAME <name>
```
4. Save the file. The file is saved automatically with the name GLOBALS, *without a file extension*. Do not move this file. It is referenced during installation of the Windows service and during data processing.

Installing Manager as a Windows service

By default, Manager is not installed as a service and can be run by a local or domain account. However, when run this way, Manager will stop when the user logs out. When you install Manager as a service, you can operate it independently of user connections, and you can configure it to start manually or at system start-up. Installing Manager as a service is required on a Windows Cluster, but optional otherwise.

To install Manager as a Windows service

1. (Recommended) Log on as the system administrator.
2. Click **Start > Run**, and type **cmd** in the **Run** dialog box.
3. From the directory that contains the Manager program that you are installing as a service, run the **install** program with the following syntax:

```
install <option> [...]
```

Where: <option> is one of the following:

Table 3 INSTALL options

Option	Description
ADDEVENTS	Adds Oracle GoldenGate events to the Windows Event Manager. By default, Oracle GoldenGate errors are generic. To produce more specific error content, copy the following files from the Oracle GoldenGate installation directory to the SYSTEM32 directory. category.dll ggmsg.dll

Table 3 INSTALL options (continued)

Option	Description
ADDSERVICE	<p>Adds Manager as a service by the name specified in the GLOBALS file, if one exists, or by the default of GGSMGR. ADDSERVICE configures the service to run as the Local System account, the standard for most Windows applications because the service can be run independently of user logins and password changes. To run Manager as a specific account, use the USER and PASSWORD options.¹</p> <p>The service is installed to start at system boot time (see AUTOSTART). To start it after installation, either reboot the system, or start the service manually from the Services applet of the Control Panel.</p>
AUTOSTART	Specifies that the service created with ADDSERVICE is to be started at system boot time. This is the default unless MANUALSTART is used.
MANUALSTART	Specifies that the service created with ADDSERVICE is to be started manually through GGSCI, a script, or the Services applet of the Control Panel. The default is AUTOSTART.
USER <name>	<p>Specifies a domain user account for executing Manager. For <name>, include the domain name, a backward slash, and the user name, for example HEADQT\GGSMGR.</p> <p>By default, the Manager service is installed to use the Local System account.</p>
PASSWORD <password>	Specifies the password for the user specified with USER.

¹ A user account can be changed by selecting the Properties action from the Services applet of the Windows Control Panel.

4. (Windows Server 2008) If Windows User Account Control (UAC) is enabled, you are prompted to allow or deny the program access to the computer. Select **Allow** to enable the install program to run. This installs the Manager service with a local system account running with administrator privileges. No further UAC prompts will be encountered when running Manager if installed as a service.

NOTE If Manager is not installed as a service, Oracle GoldenGate users will receive a UAC prompt to confirm the elevation of privileges for Manager when it is started from the GGSCI command prompt. Running other Oracle GoldenGate programs also will trigger a prompt.

Adding Oracle GoldenGate as a Windows cluster resource

If you installed Oracle GoldenGate into a cluster, follow these instructions to establish Oracle GoldenGate as a cluster resource and configure the Manager service correctly on all nodes.

1. In the Cluster Administrator, select **File>New>Resource**.

2. In the New Resource dialog box, provide a descriptive name for the Oracle GoldenGate Manager (need not be its actual name). For Resource Type, select Generic Service. For Group, select the group that contains the database instance to which Oracle GoldenGate will connect.
3. Click **Next**.
4. In the Possible Owners dialog box, select the nodes on which Oracle GoldenGate will run.
5. Click **Next**.
6. In the GGS Manager Service Properties dialog box, click the Dependencies tab, and add the following to the Resource dependencies list:
 - The database resource group
 - The disk resource containing the Oracle GoldenGate directory
 - The disk resource containing the database transaction log files
 - The disk resource containing the database transaction log backup files
7. Click **Apply**, then **OK**.
8. In the Generic Service Parameters dialog box, type either the default Manager service name of GGS_MGR or, if applicable, the custom name specified in the GLOBALS file.
9. Click **Next**.
10. Click **Finish** to exit the wizard.
11. In the Cluster Administrator tree, right-click the Manager resource and select Properties.
12. Click the Advanced tab, and deselect Affect the Group. This is a recommendation, but you can configure it as needed for your environment.
13. Click **Apply**.
14. Bring the cluster resource online to verify that it was installed correctly.
15. Take the resource offline again.
16. Move the group to the next node in the cluster. When the group has been successfully moved to the second node, the Manager resource should still be offline.
17. Log onto the second node.
18. Install Oracle GoldenGate Manager as a service on this node by running the **install** program as you did on the previous node. If you created a custom name for Manager in the GLOBALS file, that name will be used.
19. Bring the resource online to verify that it is running correctly on this node.
20. Repeat from step 16 for each additional node in the cluster.

Configuring Manager and other processes

- To use Oracle GoldenGate, you must configure the Manager process. You must specify a TCP/IP port for Manager to use, and you can specify optional parameters that control dynamic port assignments, trail file maintenance, and other properties.
- To configure other required processes, Oracle GoldenGate security, and other features that enable you to customize Oracle GoldenGate, see the *Oracle GoldenGate Windows and UNIX Administrator's Guide*.

CHAPTER 3

Uninstalling Oracle GoldenGate

.....

This procedure assumes that you no longer need the data in the Oracle GoldenGate trails, and that you no longer need to preserve the current Oracle GoldenGate environment. To preserve your current environment and data, make a backup of the Oracle GoldenGate directory and all subdirectories before starting this procedure.

Uninstalling Oracle GoldenGate from UNIX

1. Run the command shell.
2. (Suggested) Log on as the system administrator, or as a user with permission to issue Oracle GoldenGate commands, and to delete files and directories from the operating system.
3. Change directories to the Oracle GoldenGate installation directory.
4. Run GGSCI.
5. Stop all Oracle GoldenGate processes.
6. Stop the Manager process.
7. Exit GGSCI.
8. Remove the Oracle GoldenGate files by removing the installation directory.
9. Drop any Oracle GoldenGate-related objects from the database as needed.

Uninstalling Oracle GoldenGate from Windows (non-cluster)

1. (Suggested) Log on as the system administrator or as a user with permission to issue Oracle GoldenGate commands and to delete files and directories from the operating system.
2. From the Oracle GoldenGate installation folder, run GGSCI.
3. Stop all Oracle GoldenGate processes.
4. Stop the Manager program or service.
5. Exit GGSCI.
6. Click **Start > Run**, and type cmd in the **Run** dialog box to open the command console.

.....

7. Change directories to the Oracle GoldenGate installation directory.

8. Run the install program using the following syntax.

```
install deletesevents deletesevice
```

This command stops Oracle GoldenGate events from being reported to the Windows Event Manager and removes the Manager service.

9. Delete the CATEGORY.DLL and GGSMMSG.DLL files from the Windows SYSTEM32 folder.

10. Delete the Oracle GoldenGate installation folder.

11. Drop any Oracle GoldenGate-related objects from the database as needed.

Uninstalling Oracle GoldenGate from Windows Cluster

1. Working from the node in the cluster that owns the cluster group that contains the Manager resource, run GGSCI and then stop any Extract and Replicat processes that are still running.

2. Use the Cluster Administrator tool to take the Manager resource offline.

3. Right click the resource and select **Delete** to remove it.

4. Click **Start > Run**, and type cmd in the **Run** dialog box to open the command console.

5. Change directories to the Oracle GoldenGate installation directory.

6. Run the install program using the following syntax.

```
install deletesevents deletesevice
```

This command stops Oracle GoldenGate events from being reported to the Windows Event Manager and removes the Manager service.

7. Delete the CATEGORY.DLL and GGSMMSG.DLL files from the Windows SYSTEM32 folder.

8. Move the cluster group to the next node in the cluster, and repeat from step 4.

9. Delete the Oracle GoldenGate installation folder.

10. Drop any Oracle GoldenGate-related objects from the database as needed.

APPENDIX 1

Oracle GoldenGate installed components



This appendix describes the programs, directories, and other components created or used by the Oracle GoldenGate software in the Oracle GoldenGate installation directory. Additional files not listed here might be installed on certain platforms. Files listed here might not be installed on every platform.

Oracle GoldenGate Programs and Utilities

This section describes programs installed in the root Oracle GoldenGate installation directory.

NOTE Some programs may not exist in all installations. For example, if only capture or delivery is supported by Oracle GoldenGate for your platform, the extract or replicat program will not be installed, respectively. Likewise, special files might be installed to support a specific database.

Table 4 Programs and utilities

Program	Description
cobgen	Generates source definitions based on COBOL layouts. Used for Oracle GoldenGate for Datawise on Stratus.
convchk	Converts checkpoint files to a newer version.
ddlcob	Generates target DDL table creation statements based on COBOL layouts. Used for Oracle GoldenGate for Datawise on Stratus.
defgen	Generates data definitions and is referenced by Oracle GoldenGate processes when source and target tables have dissimilar definitions.
emslnt	Sends event messages created by Collector and Replicat on Windows or UNIX systems to EMS on NonStop systems.
extract	Performs capture from database tables or transaction logs or receives transaction data from a vendor access module.
ggmxinstall	Oracle GoldenGate installation script for the SQL/MX database.



Table 4 Programs and utilities (continued)

Program	Description
ggsci	User interface to Oracle GoldenGate for issuing commands and managing parameter files.
ggsmgr.jcl ggsmgr.proc ggsmgrst.jcl ggsmgrst.proc	Start the Oracle GoldenGate Manager process from a batch job or the operator console on a z/OS system. Installed to support DB2 z/OS databases.
install	Installs Oracle GoldenGate as a Windows service and provides other Windows-based service options.
keygen	Generates data-encryption keys.
logdump	A utility for viewing and saving information stored in extract trails or files.
mgr	(Manager) Control process for resource management, control and monitoring of Oracle GoldenGate processes, reporting, and routing of requests through the GGSCI interface.
replicat	Applies data to target database tables.
reverse	A utility that reverses the order of transactional operations, so that Replicat can be used to back out changes from target tables, restoring them to a previous state.
server	The Collector process, an Extract TCP/IP server collector that writes data to remote trails.
vamserv	Started by Extract to read the TMF audit trails generated by TMF-enabled applications. Installed to support the NonStop SQL/MX database.

Oracle GoldenGate subdirectories

This section describes the subdirectories of the Oracle GoldenGate installation directory and their contents.

NOTE Some directories may not exist in all installations.

Table 5 Subdirectories

Directory	Description
dirchk	<p>Contains the checkpoint files created by Extract and Replicat processes, which store current read and write positions to support data accuracy and fault tolerance. Written in internal Oracle GoldenGate format.</p> <p>File name format is <group name><sequence number>.<ext> where <sequence number> is a sequential number appended to aged files and <ext> is either cpe for Extract checkpoint files or cpr for Replicat checkpoint files.</p> <p>Do not edit these files.</p> <p>Examples: ext1.cpe rep1.cpr</p>
dirdat	<p>The default location for Oracle GoldenGate trail files and extract files that are created by Extract processes to store extracted data for further processing by the Replicat process or another application or utility. Written in internal Oracle GoldenGate format.</p> <p>File name format is a user-defined two-character prefix followed by either a six-digit sequence number (trail files) or the user-defined name of the associated Extract process group (extract files).</p> <p>Do not edit these files.</p> <p>Examples: rt000001 finance</p>
dirdef	<p>The default location for data definitions files created by the DEFGEN utility to contain source or target data definitions used in a heterogeneous synchronization environment. Written in external ASCII. File name format is a user-defined name specified in the DEFGEN parameter file.</p> <p>These files may be edited to add definitions for newly created tables. If you are unsure of how to edit a definitions file, contact Oracle GoldenGate technical support.</p> <p>Example: defs.dat</p>
dirout	This directory is not used any more.

Table 5 Subdirectories (continued)

Directory	Description
dirpcs	<p>Default location for status files. File name format is <group>.<extension> where <group> is the name of the group and <extension> is either pce (Extract), pcr (Replicat), or pcm (Manager).</p> <p>These files are only created while a process is running. The file shows the program name, the process name, the port number, and the process ID.</p> <p>Do not edit these files.</p> <p>Examples: mgr.pcm ext.pce</p>
dirprm	<p>The default location for Oracle GoldenGate parameter files created by Oracle GoldenGate users to store run-time parameters for Oracle GoldenGate process groups or utilities. Written in external ASCII format. File name format is <group name/user-defined name>.prm or mgr.prm.</p> <p>These files may be edited to change Oracle GoldenGate parameter values after stopping the process. They can be edited directly from a text editor or by using the EDIT PARAMS command in GGSCI.</p> <p>Examples: defgen.prm finance.prm</p>
dirrec	<p>Not used by Oracle GoldenGate.</p>
dirrpt	<p>The default location for process report files created by Extract, Replicat, and Manager processes to report statistical information relating to a processing run. Written in external ASCII format.</p> <p>File name format is <group name><sequence number>.rpt where <sequence number> is a sequential number appended to aged files.</p> <p>Do not edit these files.</p> <p>Examples: fin2.rpt mgr4.rpt</p>
dirtmp	<p>The default location for storing large transactions when the size exceeds the allocated memory size. Do not edit these files.</p>
dirver	<p>An Oracle GoldenGate Veridata directory. Not used unless this software is installed in the Oracle GoldenGate location.</p>

Other Oracle GoldenGate files

This section describes other files, templates, and objects created or installed in the root Oracle GoldenGate installation directory.

NOTE Some files may not be installed in your environment, depending on the database and OS platform.

Table 6 Other files

Component	Description
bcpfmt.tpl	Template for use with Replicat when creating a run file for the Microsoft BCP/DTS bulk-load utility.
blowfish.txt	Blowfish encryption software license agreement.
category.dll	Windows dynamic link library used by the INSTALL program.
chkpt_<db>_create.sql	Script that creates a checkpoint table in the local database. A different script is installed for each database type.
db2cntl.tpl	Template for use with Replicat when creating a control file for the IBM LOADUTIL bulk-load utility.
ddl_cleartrace.sql	Script that removes the DDL trace file. (Oracle installations)
ddl_disable.sql	Script that disables the Oracle GoldenGate DDL trigger. (Oracle installations)
ddl_enable.sql	Script that enables the Oracle GoldenGate DDL trigger. (Oracle installations)
ddl_ora9.sql	A script that gets tablespace information from an Oracle 9 database.
ddl_ora10.sql	A script that disables the Oracle recyclebin and gets tablespace information from an Oracle 10 database.
ddl_pin.sql	Script that pins DDL tracing, the DDL package, and the DDL trigger for performance improvements. (Oracle installations)
ddl_remove.sql	Script that removes the DDL extraction trigger and package. (Oracle installations)
ddl_setup.sql	Script that installs the Oracle GoldenGate DDL extraction and replication objects. (Oracle installations)
ddl_status.sql	Script that verifies whether or not each object created by the Oracle GoldenGate DDL support feature exists and is functioning properly. (Oracle installations)

Table 6 Other files (continued)

Component	Description
ddl_tracelevel.sql	Script that sets the level of tracing for the DDL support feature. (Oracle installations)
debug files	Debug text files that may be present if tracing was turned on.
demo_<db>_create.sql	Script that creates demonstration tables in the database associated with the Oracle GoldenGate installation.
demo_<db>_insert.sql	Script that inserts initial test data into the demonstration tables.
demo_<db>_misc.sql	Script that simulates transaction activity on the demonstration tables.
ENCKEYS	User-created file that stores encryption keys. Written in external ASCII format.
exitdemo.c	User exit example.
ggmessage.dat	Data file that contains error, informational, and warning messages that are returned by the Oracle GoldenGate processes. The version of this file is checked upon process startup and must be identical to that of the process in order for the process to operate.
ggserr.log	File that logs processing events, messages, errors, and warnings generated by Oracle GoldenGate.
ggsmsg.dll	Windows dynamic link library used by the INSTALL program.
GLOBALS	User-created file that stores parameters applying to the Oracle GoldenGate instance as a whole.
help.txt	Help file for the GGSCI command interface.
LGPL.txt	Lesser General Public License statement. Applies to free libraries from the Free Software Foundation.
libxml2.dll	Windows dynamic link library containing the XML library for the Oracle GoldenGate XML procedures.
libxml2.txt	License agreement for libxml2.dll.
marker.hist	File created by Replicat if markers were passed from a NonStop source system.
marker_remove.sql	Script that removes the DDL marker table. (Oracle installations)

Table 6 Other files (continued)

Component	Description
marker_setup.sql	Script that installs the Oracle GoldenGate DDL marker table. (Oracle installations)
marker_status.sql	Script that confirms successful installation of the DDL marker table. (Oracle installations)
params.sql	Script that contains configurable parameters for DDL support. (Oracle installations)
pthread-win32.txt	License agreement for pthread-VC.dll.
pthread-VC.dll	POSIX threads library for Microsoft Windows.
role_setup.sql	Script that creates the database role necessary for Oracle GoldenGate DDL support. (Oracle installations)
sqlldr.tpl	Template for use with Replicat when creating a control file for the Oracle SQL*Loader bulk-load utility.
start.prm stop.prm	z/OS parmlib members to start and stop the Manager process.
startmgr stopmgr	z/OS Unix System Services scripts to start the Manager process from GGSCI.
startmgrcom stopmgrcom	z/OS system input command for the Manager process.
tcperrs	File containing user-defined instructions for responding to TCP/IP errors.
usrdecs.h	Include file for user exit API.
zlib.txt	License agreement for zlib compression library.

Oracle GoldenGate checkpoint table

When database checkpoints are being used, Oracle GoldenGate creates a checkpoint table with a user-defined name in the database upon execution of the ADD CHECKPOINTTABLE command, or a user can create the table by using the chkpt_<db>_create.sql script, where <db> is the type of database.

Do not change the names or attributes of the columns in this table. You can change table storage attributes as needed.

Table 7 Checkpoint table definitions

Column	Description
GROUP_NAME (primary key)	The name of a Replicat group using this table for checkpoints. There can be multiple Replicat groups using the same table.
GROUP_KEY (primary key)	A unique identifier that, together with GROUPNAME, uniquely identifies a checkpoint regardless of how many Replicat groups are writing to the same table.
SEQNO	The sequence number of the checkpoint file.
RBA	The relative byte address of the checkpoint in the file.
AUDIT_TS	The timestamp of the checkpoint position in the checkpoint file.
CREATE_TS	The date and time when the checkpoint table was created.
LAST_UPDATE_TS	The date and time when the checkpoint table was last updated.
CURRENT_DIR	The current Oracle GoldenGate home directory or folder.

Index

.....

Symbols

\$LD_LIBRARY_PATH variable 11

\$PATH variable 10, 11

A

ADDEVENTS Windows service option 13

ADDSERVICE Windows service option 14

AUTOSTART Windows service option 14

C

category.dll 13

characters

supported in object names 7

cluster, installing on 4, 12, 14

connections, to database 6

CREATE SUBDIRS command 11

D

database requirements 6

disk requirements 4

E

environment variables, setting 10

F

firewall, configuring 5

G

ggmessage.dat file 24

GGSMGR default Manager name 12

ggsmsg.dll 13

GLOBALS file 13

I

installing on

Linux and UNIX 11

Windows 12

Itanium preinstallation requirements 5

K

key

name, supported characters 7

L

LIBPATH variable 11

libraries, Visual C++ 5

Linux, installing on 11

M

Manager

as Windows service 13

multiple on same system 12

name, customizing 12

MANUALSTART Windows service option 14

Memory requirements for Oracle GoldenGate 3

MGRSERVNAME parameter 13

Microsoft Visual C++ 2005 SP1 Redistributable Package 5

N

name

non-supported characters in 8

supported characters in 7

O

Oracle GoldenGate

- installed programs and files 19
- installing 9
- uninstalling 17

P

PASSWORD Windows service option 14

platforms, supported 3

ports, required by Oracle GoldenGate 5

privileges

- database 6
- operating system 5

R

removing

- Oracle GoldenGate from system 17

S

SHLIB_PATH variable 11

spaces

- in folder names 12

subdirectories, creating 11

T

TCP/IP, configuring 5

U

uninstalling Oracle GoldenGate 17

UNIX, installing on 11

USER Windows service option 14

user, Oracle GoldenGate 6

USERID parameter 6

V

VAMSERV program 20

vcredist_IA64.exe runtime library 5

virtual machine, support for 5

Visual C ++ 2005 SP1 Redistributable Package 5

W

Windows, installing on 12